# **Packet Sniffer Docs**

## version

### **Author Name**

February 04, 2025

# Contents

Welcome to Packet Sniffer Documentation!	1
packetSniffer	1
filters module	1
parser module	1
pktsniffer module	
utils module	3
Module Documentation	4
Index	Ş
Python Module Index	11

## **Welcome to Packet Sniffer Documentation!**

## packetSniffer

### filters module

filters.apply\_filters (packets, filter\_type, value)

Apply filters to the list of packets based on the filter type and value.

#### Parameters:

- packets (list) List of packet dictionaries.
- filter\_type (str) Type of filter ('host', 'port', 'ip', 'protocol', 'net').
- value (str) Filter value to apply.

**Returns:** Filtered list of packets.

Return type: list

### parser module

parser.parse\_pcap (filename)

Parses a pcap (Packet Capture) file and extracts Ethernet, IPv4, and IPv6 header details along with transport layer information (TCP/UDP).

The function reads packets from a given pcap file, processes each packet's Ethernet, IP (IPv4 or IPv6), and transport layer (TCP/UDP) headers, and returns a list of dictionaries with the parsed packet details.

#### **Parameters:**

filename: str

The name of the pcap file to be parsed. The file should be in binary format.

#### **Returns:**

#### List[dict]

A list of dictionaries, where each dictionary contains the following key-value pairs for a single packet:

- "packet\_number" (int): The packet number in the pcap file.
- "timestamp" (float): The timestamp of the packet.
- "packet\_size" (int): The size of the packet in bytes.
- "src\_mac" (str): The source MAC address in the format "xx:xx:xx:xx:xx:xx:xx.".
- "dst\_mac" (str): The destination MAC address in the format "xx:xx:xx:xx:xx:xx".
- "eth\_type" (int): The Ethernet type field (e.g., 0x0800 for IPv4, 0x86dd for IPv6).
- "ip\_version" (int or None): The IP version (4 for IPv4, 6 for IPv6), or None if not applicable.
- "header\_length" (int or None): The IP header length in bytes, or None if not applicable.
- "tos" (int or None): The Type of Service field in the IPv4 header, or None if not applicable.
- "total\_length" (int or None): The total length of the IP packet, or None if not applicable.
- "identification" (int or None): The IP identification field, or None if not applicable.
- "flags" (int or None): The flags field in the IP header, or None if not applicable.
- "fragment\_offset" (int or None): The fragment offset field in the IP header, or None if not applicable.
- "ttl" (int or None): The Time to Live (TTL) field in the IP header, or None if not applicable.

- "protocol" (str): The protocol used at the transport layer (e.g., "TCP", "UDP", "ICMP"), or a descriptive string for unknown protocols.
- "header\_checksum" (int or None): The checksum of the IP header, or None if not applicable.
- "src\_ip" (str or None): The source IP address (in IPv4 or IPv6 format), or None if not applicable.
- "dst\_ip" (str or None): The destination IP address (in IPv4 or IPv6 format), or None if not applicable.
- "src port" (int or None): The source port for TCP/UDP packets, or None if not applicable.
- "dst\_port" (int or None): The destination port for TCP/UDP packets, or None if not applicable.

#### **Notes:**

- · For Ethernet frames, the function assumes that the packets are either IPv4 or IPv6 packets.
- For IPv4 packets, both TCP and UDP transport layer protocols are supported.
- For IPv6 packets, only the transport layer protocols that are commonly used (TCP/UDP) are considered.
- The packet data for IPv4 and IPv6 is processed and the associated transport layer data is extracted when applicable.
- If the packet is not an IPv4 or IPv6 packet, the relevant IP-specific fields (such as *ip\_version*, *src\_ip*, *dst\_ip*, etc.) will be set to *None*.

#### **Example:**

## pktsniffer module

```
pktsniffer.main()
pktsniffer.print_packet_details(packet)
```

This function takes a packet (represented as a dictionary) and displays its details in a human-readable format, including Ethernet, IP, and transport layer information (TCP/UDP/ICMP). The packet's number, timestamp, MAC addresses, protocol details, and other header information are printed for easy inspection.

#### **Parameters:**

#### packet: dict

A dictionary containing the parsed details of a network packet, including the following keys:

- "packet\_number" (int): The packet number in the pcap file.
- "timestamp" (float): The timestamp of the packet.
- "packet\_size" (int): The size of the packet in bytes.
- "src\_mac" (str): The source MAC address in the format "xx:xx:xx:xx:xx:xx.".
- "dst\_mac" (str): The destination MAC address in the format "xx:xx:xx:xx:xx:xx".
- "eth\_type" (int): The Ethernet type field (e.g., 0x0800 for IPv4, 0x86dd for IPv6).
- "ip\_version" (int or None): The IP version (4 for IPv4, 6 for IPv6), or None if not applicable.
- "header\_length" (int or None): The IP header length in bytes, or None if not applicable.

- "tos" (int or None): The Type of Service field in the IPv4 header, or None if not applicable.
- "total\_length" (int or None): The total length of the IP packet, or None if not applicable.
- "identification" (int or None): The IP identification field, or None if not applicable.
- "flags" (int or None): The flags field in the IP header, or None if not applicable.
- "fragment\_offset" (int or None): The fragment offset field in the IP header, or None if not applicable.
- "ttl" (int or None): The Time to Live (TTL) field in the IP header, or None if not applicable.
- "protocol" (str): The protocol used at the transport layer (e.g., "TCP", "UDP", "ICMP").
- "header\_checksum" (int or None): The checksum of the IP header, or None if not applicable.
- "src\_ip" (str or None): The source IP address (in IPv4 or IPv6 format), or None if not applicable.
- "dst\_ip" (str or None): The destination IP address (in IPv4 or IPv6 format), or None if not applicable.
- "src\_port" (int or None): The source port for TCP/UDP packets, or None if not applicable.
- "dst\_port" (int or None): The destination port for TCP/UDP packets, or None if not applicable.

#### **Example:**

#### utils module

```
utils.format_ip (address)
```

Convert an IP address to a readable format.

This function takes an IP address as a byte sequence (in IPv4 format) and returns a string representation of the address in the standard "xxx.xxx.xxx" format.

#### **Parameters:**

#### address: bytes

The IP address as a sequence of 4 bytes.

#### **Returns:**

str

The IP address as a formatted string, e.g., "192.168.1.1".

#### **Example:**

```
>>> format_ip(b'À"■■')
'192.168.1.1'

utils.format_mac (address)
```

Convert a MAC address to a readable format.

This function takes a MAC address as a byte sequence and returns a string representation of the address in the standard "xx:xx:xx:xx:xx" format, where "xx" represents a two-digit hexadecimal value for each byte.

#### **Parameters:**

address: bytes

The MAC address as a sequence of 6 bytes.

#### **Returns:**

str

The MAC address as a formatted string, e.g., "00:1a:2b:3c:4d:5e".

### **Example:**

```
>>> format_mac(b'\ +<M^')
'00:1a:2b:3c:4d:5e'
```

## **Module Documentation**

```
pktsniffer.print_packet_details (packet)
```

This function takes a packet (represented as a dictionary) and displays its details in a human-readable format, including Ethernet, IP, and transport layer information (TCP/UDP/ICMP). The packet's number, timestamp, MAC addresses, protocol details, and other header information are printed for easy inspection.

### **Parameters:**

packet: dict

A dictionary containing the parsed details of a network packet, including the following keys:

- "packet\_number" (int): The packet number in the pcap file.
- "timestamp" (float): The timestamp of the packet.
- "packet\_size" (int): The size of the packet in bytes.
- "src\_mac" (str): The source MAC address in the format "xx:xx:xx:xx:xx:xx:xx".
- "dst\_mac" (str): The destination MAC address in the format "xx:xx:xx:xx:xx:xx".
- "eth\_type" (int): The Ethernet type field (e.g., 0x0800 for IPv4, 0x86dd for IPv6).
- "ip\_version" (int or None): The IP version (4 for IPv4, 6 for IPv6), or None if not applicable.
- "header\_length" (int or None): The IP header length in bytes, or None if not applicable.
- "tos" (int or None): The Type of Service field in the IPv4 header, or None if not applicable.
- "total\_length" (int or None): The total length of the IP packet, or None if not applicable.
- "identification" (int or None): The IP identification field, or None if not applicable.
- "flags" (int or None): The flags field in the IP header, or None if not applicable.
- "fragment\_offset" (int or None): The fragment offset field in the IP header, or None if not applicable.
- "ttl" (int or None): The Time to Live (TTL) field in the IP header, or None if not applicable.
- "protocol" (str): The protocol used at the transport layer (e.g., "TCP", "UDP", "ICMP").
- "header\_checksum" (int or None): The checksum of the IP header, or None if not applicable.
- "src\_ip" (str or None): The source IP address (in IPv4 or IPv6 format), or None if not applicable.
- "dst\_ip" (str or None): The destination IP address (in IPv4 or IPv6 format), or None if not applicable.
- "src\_port" (int or None): The source port for TCP/UDP packets, or None if not applicable.
- "dst\_port" (int or None): The destination port for TCP/UDP packets, or None if not applicable.

## **Example:**

parser.parse\_pcap (filename)

Parses a pcap (Packet Capture) file and extracts Ethernet, IPv4, and IPv6 header details along with transport layer information (TCP/UDP).

The function reads packets from a given pcap file, processes each packet's Ethernet, IP (IPv4 or IPv6), and transport layer (TCP/UDP) headers, and returns a list of dictionaries with the parsed packet details.

### **Parameters:**

filename: str

The name of the pcap file to be parsed. The file should be in binary format.

### **Returns:**

#### List[dict]

A list of dictionaries, where each dictionary contains the following key-value pairs for a single packet:

- "packet\_number" (int): The packet number in the pcap file.
- "timestamp" (float): The timestamp of the packet.
- "packet size" (int): The size of the packet in bytes.
- "src\_mac" (str): The source MAC address in the format "xx:xx:xx:xx:xx:xx".
- "dst\_mac" (str): The destination MAC address in the format "xx:xx:xx:xx:xx:xx".
- "eth\_type" (int): The Ethernet type field (e.g., 0x0800 for IPv4, 0x86dd for IPv6).
- "ip\_version" (int or None): The IP version (4 for IPv4, 6 for IPv6), or None if not applicable.
- "header\_length" (int or None): The IP header length in bytes, or None if not applicable.
- "tos" (int or None): The Type of Service field in the IPv4 header, or None if not applicable.
- "total\_length" (int or None): The total length of the IP packet, or None if not applicable.
- "identification" (int or None): The IP identification field, or None if not applicable.
- "flags" (int or None): The flags field in the IP header, or None if not applicable.
- "fragment\_offset" (int or None): The fragment offset field in the IP header, or None if not applicable.
- "ttl" (int or None): The Time to Live (TTL) field in the IP header, or None if not applicable.
- "protocol" (str): The protocol used at the transport layer (e.g., "TCP", "UDP", "ICMP"), or a descriptive string for unknown protocols.
- "header\_checksum" (int or None): The checksum of the IP header, or None if not applicable.
- "src\_ip" (str or None): The source IP address (in IPv4 or IPv6 format), or None if not applicable.
- "dst\_ip" (str or None): The destination IP address (in IPv4 or IPv6 format), or None if not applicable.
- "src\_port" (int or None): The source port for TCP/UDP packets, or None if not applicable.
- "dst\_port" (int or None): The destination port for TCP/UDP packets, or None if not applicable.

### **Notes:**

- For Ethernet frames, the function assumes that the packets are either IPv4 or IPv6 packets.
- For IPv4 packets, both TCP and UDP transport layer protocols are supported.
- For IPv6 packets, only the transport layer protocols that are commonly used (TCP/UDP) are considered.
- The packet data for IPv4 and IPv6 is processed and the associated transport layer data is extracted when applicable.
- If the packet is not an IPv4 or IPv6 packet, the relevant IP-specific fields (such as *ip\_version*, *src\_ip*, *dst\_ip*, etc.) will be set to *None*.

### **Example:**

```
>>> parse_pcap("capture.pcap")
[{'packet_number': 1, 'timestamp': 1619190374.123456, 'packet_size': 84, 'src_mac': '00:14
        'dst_mac': '00:14:22:67:89:ab', 'eth_type': 2048, 'ip_version': 4, 'header_length': 20
        'tos': 0, 'total_length': 60, 'identification': 12345, 'flags': 2, 'fragment_offset':
        'ttl': 64, 'protocol': 'TCP', 'header_checksum': 0x1234, 'src_ip': '192.168.1.1',
        'dst_ip': '192.168.1.2', 'src_port': 80, 'dst_port': 12345},
... ]
```

filters.apply\_filters (packets, filter\_type, value)

Apply filters to the list of packets based on the filter type and value.

#### Parameters:

- packets (list) List of packet dictionaries.
- filter\_type (str) Type of filter ('host', 'port', 'ip', 'protocol', 'net').
- value (str) Filter value to apply.

**Returns:** Filtered list of packets.

Return type: list

```
utils.format_ip (address)
```

Convert an IP address to a readable format.

This function takes an IP address as a byte sequence (in IPv4 format) and returns a string representation of the address in the standard "xxx.xxx.xxx" format.

### **Parameters:**

address: bytes

The IP address as a sequence of 4 bytes.

#### **Returns:**

str

The IP address as a formatted string, e.g., "192.168.1.1".

## **Example:**

```
>>> format_ip(b'À"■■')
'192.168.1.1'
```

```
utils.format_mac (address)
```

Convert a MAC address to a readable format.

This function takes a MAC address as a byte sequence and returns a string representation of the address in the standard "xx:xx:xx:xx:xx" format, where "xx" represents a two-digit hexadecimal value for each byte.

#### Parameters:

## **Parameters:**

address: bytes

The MAC address as a sequence of 6 bytes.

## **Returns:**

str

The MAC address as a formatted string, e.g., "00:1a:2b:3c:4d:5e".

## **Example:**

```
>>> format_mac(b'=+<M^')
'00:1a:2b:3c:4d:5e'
```

# Index

```
apply_filters() (in module filters) [1]
F
filters
    module [1]
format_ip() (in module utils) [1]
format_mac() (in module utils) [1]
M
main() (in module pktsniffer)
module
    filters [1]
    parser [1]
    pktsniffer [1]
    utils [1]
P
parse_pcap() (in module parser) [1]
parser
    module [1]
pktsniffer
    module [1]
print_packet_details() (in module pktsniffer) [1]
U
utils
    module [1]
```

# **Python Module Index**

f

filters

n

parser

pktsniffer

u

utils